Configuring Front

Configuring Front for single sign-on (SSO) enables administrators to manage users of Citrix ADC. Users can securely log on to Front by using the enterprise credentials.

Prerequisite

Browser Requirements: Internet Explorer 11 and above

To configure Front for SSO by using SAML:

- 1. In a browser, type <u>https://frontapp.com/</u> and press **Enter**.
- 2. Type your Front admin credentials (Your email and Your password) and click Sign In.



3. In the top-left corner, click the user account icon and select **Settings** from the drop-down menu.

Q O	Q , Search		× •
	OPEN	ALL	
Settings			
Help center			
C Talk to us			
Recommend Front	No assigned	d conversations	5.
What's new	View all	conversations	
🕛 Logout			

4. In the left panel, scroll down and click **Preferences** under **COMPANY**.

COMPANY
Teams
Teammates
Inboxes
Rules
Responses
Signatures
Tags
Roles & Permissions
Contacts
Integrations
Plugins & API
Preferences
Billing

5. In the **Company preferences** page, click **Single Sign On**.

Company preferenc	es	
General Single Sign On	Bump on comment Move a conversation to the top when a new comment is posted	
	Bump on assign Move a conversation to the top when it's assigned	
	Allow non-administrators to delete conversations Disable if you want regular users to always archive	
	Allow conversations to be moved to all team inboxes Enable to let teammates move to team inboxes they cannot access	
	Session idle timeout Log out user if idle for more than this period of time	Never ~

6. Scroll down and enter the values for the following fields in **SAML Integration**:

Field Name	Description
SSO	Select SAML from the drop-down list.
ENTRY POINT	IdP logon URL
Authentication request binding	Select HTTP Post from the drop-down list.
Signing Certificate	Copy and paste the IdP certificate. The IdP certificate must begin and end with Begin CertificateandEnd Certificate
	Note: The IdP Certificate is provided by Citrix and can be accessed from the link below: https://ssb4.mgmt.netscalergatewaydev.net/idp/saml/templatetest/i

	SAML ~
nabling Single Sign On (SSO) will forc	Disable g the method of yo
	SAML 🗸
Read ou	r SSO documentation.
ITRY POINT	
UDL of your identity provider	which will receive authentication requests
URL of your identity provider	which will receive authentication requests
URL of your identity provider	which will receive authentication requests
URL of your identity provider	which will receive authentication requests
URL of your identity provider	which will receive authentication requests
URL of your identity provider hentication request binding hod with which the authentication req	which will receive authentication requests HTTP Pos
URL of your identity provider hentication request binding hod with which the authentication req	which will receive authentication requests HTTP Pos
URL of your identity provider hentication request binding hod with which the authentication req ning certificate	which will receive authentication requests uest will be sent to your identity pro
URL of your identity provider thentication request binding hod with which the authentication req ning certificate	which will receive authentication requests Juest will be sent to your identity pro
URL of your identity provider chentication request binding hod with which the authentication req ning certificate	which will receive authentication requests uest will be sent to your identity pro
URL of your identity provider chentication request binding hod with which the authentication req ning certificate	which will receive authentication requests uest will be sent to your identity pro
URL of your identity provider hentication request binding hod with which the authentication req ning certificate	which will receive authentication requests guest will be sent to your identity pro
URL of your identity provider thentication request binding hod with which the authentication req ning certificate	which will receive authentication requests Juest will be sent to your identity pro
URL of your identity provider thentication request binding hod with which the authentication req ning certificate	which will receive authentication requests puest will be sent to your identity pro
URL of your identity provider thentication request binding hod with which the authentication req ning certificateBEGIN CERTIFICATE	which will receive authentication requests Juest will be sent to your identity pro
URL of your identity provider thentication request binding hod with which the authentication req ning certificate	which will receive authentication requests Juest will be sent to your identity pro