Configuring Shufflrr

Configuring Shufflrr for SSO enables administrators to manage their users using Citrix Gateway. Users can securely log on to Shufflrr using their enterprise credentials.

To configure Shufflrr for SSO through SAML, follow the steps below:

- 1. In a browser, type <u>https://login.shufflrr.com/login?ReturnUrl=%2f</u> and press **Enter**.
- 2. Type your credentials, and click **Sign In**.

⇒shufflrr		
1 Sign in		
Email		
Password		
Siç	jn In	
Remember me	Forgot Password?	
Copyright ©	2018 Shuffirr	
All rights	s reserved.	

- 3. On the Landing page, click **Admin > Settings**.
- 4. In the Authentication section, select the **SAML Single Sign-On** checkbox.

shuffl	r	口 Presentations	Browse	L Upload	y Builder	Reports	Admin
Administration	L Users	🚇 Groups	🔖 Tags	≁ Build	ers 😋	Settings	🧬 Billing

₽å Authentication	on						
Authentication Type	•	Shuffirr					
	[Salesforce					
	•	SAML Single Si	ign-On				

5. In the SAML Single Sign-On section, specify the following information:

SAML Single Sign-O	n	
Service Provider ID	https://sharvari.shufflrr.com	
Service Provider ACS URL	https://sharvari.shufflrr.com/login/samlassertionconsumerservice	
Service Provider Certificate	📩 Download	
Identity Provider Certificate	🕹 Download 🚺 Upload	
Identity Provider Issuer ID	M_MU_M_M	2
Single Sign-on Service URL	https:///saml/login	3
Enfore SAML Groups	OFF	
Sign Authentication Request	ON	
SAML Response Signed	ON	
SAML Assertion Signed	OFF	

- i. **Identity Provider Certificate**: To upload your IdP certificate, follow the steps below:
 - a. Remotely access your NetScaler instance using PuTTY.
 - b. Navigate to /nsconfig/ssl folder (using shell command cd /nsconfig/ssl) and press Enter.
 - c. Type cat <certificate-name> and press **Enter**.

1	BEGIN CERTIFICATE
2	MIIFPzCCBCegAwIBAgIQApjYl89Tw/6/mHRS5nGDUzANBgkqhkiG9w0BAQsFADBN
3	NQs = 12 The District of the District of Company of Com
4	aWc
5	NT _E
6	BAc N5j
7	LjE
8	ADC 2EQ
9	yVj 🔰 🖉 🖉 🖉 🖉 🖉 🖉 🖉 🖉
10	Kjf
11	vd8
12	RK2 31K
13	RYc 4QY
14	MBaar and an
15	+Cc /IZ
16	Y2V R01
17	BBY HA6
18	Lys
19	OIE I I I I I I I I I I I I I I I I I I
20	MDc 2Vy
21	dC5 VGG
22	GGł 2Nh
23	Y2V nNy
24	dD4 Zxf
25	PA6 (kY
26	+Xz NpI
27	gSf 3c3
28	c+r DF1
29	UOZimwmopreicnajjorinwwczikpodugrwyenwiwyinwgoaiz/mzwzdębwzy4NJ
30	6ED5
31	END CERTIFICATE
32	

- d. Copy the text between -----BEGIN CERTIFICATE----- and -----END CERTIFICATE-----
- ii. **Identity Provider Issuer ID:** type a unique issuer ID. For example: yourcompany_NS_Confluence

- iii. **Single Sign-On Service URL: E**nter the IdP URL, SAML 2.0 endpoint, for example, https://example.com/saml/login
- 6. In the Single Logout section, specify the following information:

Single Logout		
Enable Single Logout		
Service Provider SLO URL	https://ctxnsqa.shutflirr.com/logout/samisloservice	
Single Logout URL	https://ugiline.eu.cgi/logout	2
Single Logout Response URL	https://	3
Logout Request Signed		
Logout Response Signed	ON 5	
Sign Logout Request	ON 6	
Sign Logout Response		

- i. **Enable Single Logout:** Switch ON the toggle switch to enable single logout.
- ii. **Single Logout URL:** Enter the logout URL.
- iii. Single Logout Response URL: Enter the single logout response URL.
- iv. **Logout Request Signed:** Switch **ON** the toggle switch to enable Logout Request.
- v. **Logout Response Signed:** Switch **ON** the toggle switch to enable Logout Response.
- vi. **Sign Logout Request:** Switch **ON** the toggle switch to enable Sign Logout Request.
- vii. **Sign Logout Response:** Switch **ON** the toggle switch to enable Sign Logout Response.

The SAML SSO configuration is completed.