



Configuring Workplace


Users can securely log on to Workplace using their enterprise credentials. To configure Workplace for SSO through SAML, follow the steps below:



1. Login to Workplace as an Admin user.



2. Select **Admin Panel** from the left panel under the tab **Explore**.



3. **Admin Panel** window will open > Select **Authentication** from the left panel under the tab **Preferences**.

Login	Allow people to log in with: 1 <input checked="" type="checkbox"/> Password <input checked="" type="checkbox"/> SSO <small>This lets you decide how everyone in your organization logs in. If you select both, you'll be able to choose how each person logs in individually.</small> Default for new users: Password ⓘ
SAML Authentication	In web browsers, check SAML again after: 1 day 2 <input checked="" type="checkbox"/> Require SAML in mobile apps ⓘ Log people out of mobile apps after: Never ⓘ <div style="border: 1px solid #ccc; padding: 2px; display: inline-block;">Require SAML authentication for all users now</div>
SAML URL	<input type="text" value="https://ug1.██████.com/saml/login"/> 3 ⓘ
SAML Issuer URI	<input type="text" value="UG_VPN_FBWorkplace"/> 4 ⓘ
SAML Logout Redirect	<input checked="" type="checkbox"/> Enable SAML Logout Redirection ⓘ <input type="text" value="https://ug1.██████.com/cgi/logout"/> 5

SAML certificate



The certificate is valid for 122 days

SAML configuration

Audience URL

<https://www.facebook.com/company/>

Recipient URL

<https://workplace.facebook.com/work/saml.php>

ACS (Assertion Consumer Service) URL

<https://workplace.facebook.com/work/saml.php>

Test SSO

Customer id

Save

4. **Authentication Settings** window will open > Fill the template with appropriate values.

Field Name	Values
Login	Password & SSO should be checked
SAML Authentication	Required SAML in mobile apps should be checked
SAML URL	<a href="https://ug1.<customer_domain>.com/saml/login">https://ug1.<customer_domain>.com/saml/login
SAML Issuer URI	As you mentioned in IdP
SAML Logout Redirect	Enable SAML Logout Redirection should be checked <a href="https://ug1.<customer_domain>.com/cgi/logout">https://ug1.<customer_domain>.com/cgi/logout
SAML certificate	Paste IdP certificate

5. In place of <customer domain>, enter your company instance (See **Introduction** to know more about the <customer domain> value.)
6. Test the configuration using the button **Test SSO**.
7. Click **Save**.